

Data acquisition with the ADS1115 on the raspberry PI

Generated by Doxygen 1.9.1



---

<b>1 rpi_ads1115</b>	<b>1</b>
<b>2 Class Index</b>	<b>3</b>
2.1 Class List . . . . .	3
<b>3 Class Documentation</b>	<b>5</b>
3.1 ADS1115rpi Class Reference . . . . .	5
3.1.1 Detailed Description . . . . .	5
3.1.2 Member Function Documentation . . . . .	5
3.1.2.1 hasSample() . . . . .	5
3.1.2.2 setChannel() . . . . .	6
3.1.2.3 start() . . . . .	6
3.2 ADS1115settings Struct Reference . . . . .	6
3.2.1 Detailed Description . . . . .	7
<b>Index</b>	<b>9</b>



# Chapter 1

## rpi\_ads1115

Raspberry PI C++ library for the ADS1115

github: [https://github.com/berndporr/rpi\\_ads1115](https://github.com/berndporr/rpi_ads1115)



## Chapter 2

# Class Index

### 2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

#### [ADS1115rpi](#)

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available . . . . . [5](#)

#### [ADS1115settings](#)

ADS1115 initial settings when starting the device . . . . . [6](#)





## Chapter 3

# Class Documentation

### 3.1 ADS1115rpi Class Reference

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available.

```
#include <ads1115rpi.h>
```

#### Public Member Functions

- `~ADS1115rpi ()`  
*Destructor which makes sure the data acquisition stops on exit.*
- virtual void `hasSample (float sample)=0`  
*Called when a new sample is available.*
- void `setChannel (ADS1115settings::Input channel)`  
*Selects a different channel at the multiplexer while running.*
- void `start (ADS1115settings settings=ADS1115settings())`  
*Starts the data acquisition in the background and the callback is called with new samples.*
- `ADS1115settings getADS1115settings () const`  
*Returns the current settings.*
- void `stop ()`  
*Stops the data acquisition.*

#### 3.1.1 Detailed Description

This class reads data from the ADS1115 in the background (separate thread) and calls a callback function whenever data is available.

#### 3.1.2 Member Function Documentation

##### 3.1.2.1 hasSample()

```
virtual void ADS1115rpi::hasSample (  
    float sample ) [pure virtual]
```

Called when a new sample is available.

This needs to be implemented in a derived class by the client. Defined as abstract.

## Parameters

<i>sample</i>	Voltage from the selected channel.
---------------	------------------------------------

### 3.1.2.2 setChannel()

```
void ADS1115rpi::setChannel (
    ADS1115settings::Input channel )
```

Selects a different channel at the multiplexer while running.

Call this in the callback handler [hasSample\(\)](#) to cycle through different channels.

## Parameters

<i>channel</i>	Sets the channel from A0..A3.
----------------	-------------------------------

### 3.1.2.3 start()

```
void ADS1115rpi::start (
    ADS1115settings settings = ADS1115settings() )
```

Starts the data acquisition in the background and the callback is called with new samples.

## Parameters

<i>settings</i>	A struct with the settings.
-----------------	-----------------------------

The documentation for this class was generated from the following file:

- ads1115rpi.h

## 3.2 ADS1115settings Struct Reference

ADS1115 initial settings when starting the device.

```
#include <ads1115rpi.h>
```

## Public Types

- enum [SamplingRates](#) {  
**FS8HZ** = 0 , **FS16HZ** = 1 , **FS32HZ** = 2 , **FS64HZ** = 3 ,  
**FS128HZ** = 4 , **FS250HZ** = 5 , **FS475HZ** = 6 , **FS860HZ** = 7 }  
*Sampling rates.*
- enum [PGA](#) { **FSR2\_048** = 2 , **FSR1\_024** = 3 , **FSR0\_512** = 4 , **FSR0\_256** = 5 }  
*Full scale range: 2.048V, 1.024V, 0.512V or 0.256V.*
- enum [Input](#) { **AIN0** = 0 , **AIN1** = 1 , **AIN2** = 2 , **AIN3** = 3 }  
*Channel indices.*

## Public Member Functions

- unsigned [getSamplingRate](#) () const  
*Get the sampling rate in Hz.*

## Public Attributes

- int [i2c\\_bus](#) = 1  
*I2C bus used (99% always set to one)*
- uint8\_t [address](#) = DEFAULT\_ADS1115\_ADDRESS  
*I2C address of the ads1115.*
- [SamplingRates](#) [samplingRate](#) = FS8HZ  
*Sampling rate requested.*
- [PGA](#) [pgaGain](#) = FSR2\_048  
*Requested full scale range.*
- [Input](#) [channel](#) = AIN0  
*Requested input channel (AIN0..AIN3)*
- int [drdy\\_chip](#) = 0  
*GPIO Chip number which receives the Data Ready signal.*
- int [drdy\\_gpio](#) = DEFAULT\_ALERT\_RDY\_TO\_GPIO  
*GPIO pin connected to ALERT/RDY.*

### 3.2.1 Detailed Description

ADS1115 initial settings when starting the device.

The documentation for this struct was generated from the following file:

- ads1115rpi.h



# Index

- ADS1115rpi, [5](#)
  - hasSample, [5](#)
  - setChannel, [6](#)
  - start, [6](#)
- ADS1115settings, [6](#)
- hasSample
  - ADS1115rpi, [5](#)
- setChannel
  - ADS1115rpi, [6](#)
- start
  - ADS1115rpi, [6](#)